

Univention Corporate Server



Extended domain services documentation

Table of Contents

1. Integration of Ubuntu clients into a UCS domain	4
1.1. Integration into the LDAP directory and the SSL certificate authority	4
1.2. Configuration of the System Security Services Daemon (SSSD)	5
1.3. Configuring user logins	7
1.4. Kerberos integration	8
1.5. Limitations of the Ubuntu domain integration	9
1.6. Additional references	9
2. Integration of Linux/Unix systems into a UCS domain	10
2.1. Managing the systems in the Univention Management Console	10
2.2. Configuration of the name resolution	10
2.3. Configuration of the time server	10
2.4. Access to user and group information of the UCS domain	10
2.5. Integrating into Kerberos	11
2.6. Accessing a UCS print server	12

Chapter 1. Integration of Ubuntu clients into a UCS domain

Univention Corporate Server allows the integration of Ubuntu clients. Initially a standard Ubuntu installation needs to be performed. The following section describe the configuration changes, which need to be made to integrate the Ubuntu client into the UCS domain. After successful integration users can authenticate on the Ubuntu clients with their standard UCS domain password and user name.

This configuration has been tested with Ubuntu 12.04 LTS and 12.10 as well as Kubuntu 12.04 LTS and 12.10.

1.1. Integration into the LDAP directory and the SSL certificate authority Feedback

After Ubuntu has been installed, some of its configuration files need to be modified. To simplify the setup, the default configuration of the UCS master domain controller should be copied to the Ubuntu system, for example:

```
# Become root
sudo bash

# Set the IP address of the UCS DC Master, 192.168.0.3 in this example
export MASTER_IP=192.168.0.3

mkdir /etc/univention
ssh root@${MASTER_IP} ucr shell |
    grep -v ^hostname= >/etc/univention/ucr_master
echo "master_ip=${MASTER_IP}" >>/etc/univention/ucr_master
. /etc/univention/ucr_master

echo "${MASTER_IP} ${ldap_master}" >>/etc/hosts

# Exit sudo bash
exit
```

In the default configuration of UCS only authenticated users can search in the LDAP directory. As such, the Ubuntu client needs an account in the UCS domain to gain read access to the LDAP directory:

```
# Become root
sudo bash


# Set some environment variables
. /etc/univention/ucr_master

# Download the SSL certificate
mkdir -p /etc/univention/ssl/ucsCA/
wget -O /etc/univention/ssl/ucsCA/CAcert.pem \
    http://${ldap_master}/ucs-root-ca.crt

# Create an account and save the password
password="$(tr -dc A-Za-z0-9_ </dev/urandom | head -c8)"
if [ "$version_version" = 3.0 ] && [ "$version_patchlevel" -lt 2 ]
then
```

```
ssh root@${ldap_master} udm computers/managedclient create \  
  --position "cn=computers,${ldap_base}" \  
  --set name=$(hostname) --set password="${password}"  
else  
  ssh root@${ldap_master} udm computers/ubuntu create \  
  --position "cn=computers,${ldap_base}" \  
  --set name=$(hostname) --set password="${password}" \  
  --set operatingSystem="$(lsb_release -is)" \  
  --set operatingSystemVersion="$(lsb_release -rs)"  
fi  
echo "${password}" > /etc/ldap.secret  
  
# Create ldap.conf  
cat >/etc/ldap/ldap.conf <<__EOF__  
TLS_CACERT /etc/univention/ssl/ucsCA/CACert.pem  
URI ldap://$ldap_master:7389  
BASE $ldap_base  
__EOF__  
  
# Exit sudo bash  
exit
```

1.2. Configuration of the System Security Services Daemon (SSSD)

Feedback 

SSSD provides a set of daemons to manage access to remote directories and authentication mechanisms.

```
# Become root  
sudo bash  
  
# Set some environment variables  
. /etc/univention/ucr_master  
  
# Install SSSD based configuration  
DEBIAN_FRONTEND=noninteractive apt-get -y install sssd  
  
# Create sssd.conf  
cat >/etc/sss/sss.conf <<__EOF__  
[sss]  
config_file_version = 2  
reconnection_retries = 3  
sbus_timeout = 30  
services = nss, pam, sudo  
domains = $kerberos_realm  
  
[nss]  
reconnection_retries = 3  
  
[pam]  
reconnection_retries = 3  
  
[domain/$kerberos_realm]  
auth_provider = krb5  
krb5_kdcip = ${master_ip}
```

Configuration of the System Security Services Daemon (SSSD)

```
krb5_realm = ${kerberos_realm}
krb5_server = ${ldap_master}
krb5_kpasswd = ${ldap_master}
id_provider = ldap
ldap_uri = ldap://${ldap_master}:7389
ldap_search_base = ${ldap_base}
ldap_tls_reqcert = never
ldap_tls_cacert = /etc/univention/ssl/ucsCA/CAcert.pem
cache_credentials = true
enumerate = true
ldap_default_bind_dn = cn=$(hostname),cn=computers,${ldap_base}
ldap_default_authtok_type = password
ldap_default_authtok = $(cat /etc/ldap.secret)
__EOF__
chmod 600 /etc/sss/sss.conf

# Install auth-client-config
DEBIAN_FRONTEND=noninteractive apt-get -y install auth-client-config

# Create an auth config profile for sssd
cat >/etc/auth-client-config/profile.d/sss <<__EOF__
[sss]
nss_passwd=   passwd:   compat sss
nss_group=   group:    compat sss
nss_shadow=  shadow:   compat
nss_netgroup= netgroup: nis

pam_auth=
auth [success=3 default=ignore] pam_unix.so nullok_secure \
    try_first_pass
auth requisite pam_succeed_if.so uid >= 500 quiet
auth [success=1 default=ignore] pam_sss.so use_first_pass
auth requisite pam_deny.so
auth required pam_permit.so

pam_account=
account required pam_unix.so
account sufficient pam_localuser.so
account sufficient pam_succeed_if.so uid < 500 quiet
account [default=bad success=ok user_unknown=ignore] pam_sss.so
account required pam_permit.so

pam_password=
password sufficient pam_unix.so obscure sha512
password sufficient pam_sss.so use_authtok
password required pam_deny.so

pam_session=
session required pam_mkhomedir.so skel=/etc/skel/ umask=0077
session optional pam_keyinit.so revoke
session required pam_limits.so
session [success=1 default=ignore] pam_sss.so
session required pam_unix.so
__EOF__
```


```
auth-client-config -n -a -p sss

# Start sssd
service sssd start

# Exit sudo bash
exit
```

The commands `getent passwd` and `getent group` should now also display all users and groups of the UCS domain.

1.3. Configuring user logins

Feedback 

The home directory of a user should be created automatically during login:

```
# Become root
sudo bash

cat >/usr/share/pam-configs/ucs_mkhome <<__EOF__
Name: activate mkhome
Default: yes
Priority: 900
Session-Type: Additional
Session:
    required    pam_mkhome.so umask=0022 skel=/etc/skel
__EOF__

DEBIAN_FRONTEND=noninteractive pam-auth-update

exit
```

During login users should also be added to some system groups:

```
# Become root
sudo bash

echo '*;*;*;A10000-2400;audio,cdrom,dialout,floppy,plugdev,adm' \
  >>/etc/security/group.conf

cat >>/usr/share/pam-configs/local_groups <<__EOF__
Name: activate /etc/security/group.conf
Default: yes
Priority: 900
Auth-Type: Primary
Auth:
    required    pam_group.so use_first_pass
__EOF__

DEBIAN_FRONTEND=noninteractive pam-auth-update

exit
```

By default the Ubuntu login manager only displays a list of local users during login. After adding the following lines an arbitrary user name can be used:

```
# Become root
```

```

sudo bash

# Add a field for a user name
echo "greeter-show-manual-login=true" >>/etc/lightdm/lightdm.conf

# Optional: Disable the user selection at the login screen
echo "greeter-hide-users=true" >>/etc/lightdm/lightdm.conf


exit

```

Kubuntu 12.10 uses AccountService, a D-Bus interface for use account management, which ignores the /etc/lightdm.conf file. Since there is no config file for AccountService the login theme needs to be changed to *classic* under **System Settings -> Login Screen (LightDM)**.

With these settings the login for domain members should be possible after a restart of LightDM or a reboot.

1.4. Kerberos integration

 Feedback 

Every UCS domain provides a Kerberos domain. Since Kerberos relies on DNS, the Ubuntu client should use a UCS domain controller as its DNS server. The following steps provide an example configuration for Kerberos:

```

# Become root
sudo bash

# Set some environment variables
. /etc/univention/ucr_master

# Install required packages
DEBIAN_FRONTEND=noninteractive apt-get install -y heimdal-clients

# Default krb5.conf
cat >/etc/krb5.conf <<__EOF__
[libdefaults]
    default_realm = $kerberos_realm
    kdc_timesync = 1
    ccache_type = 4
    forwardable = true
    proxiable = true

[realms]
$kerberos_realm = {
    kdc = $master_ip $ldap_master
    admin_server = $master_ip $ldap_master
}
__EOF__

# Stop and disable the avahi daemon
service avahi-daemon stop
sed -i 's|start on (|start on (never and |' /etc/init/avahi-daemon.conf

# Synchronize the time with the UCS system
ntpdate $ldap_master

# Test Kerberos
kinit Administrator

```




```
# Requires domain password
krsh Administrator@$ldap_master ls /etc/univention

# Destroy the kerberos ticket
kdestroy


exit
```

1.5. Limitations of the Ubuntu domain integration

Feedback 

It is currently not possible to change the user password at the LightDM login manager. Instead, the password can be changed via the `kpasswd` command after login or via the UMC module **Change password**.

1.6. Additional references

Feedback 

- <https://help.ubuntu.com/community/LDAPClientAuthentication>
- <https://help.ubuntu.com/community/SingleSignOn>
- <https://help.ubuntu.com/community/PamCcredsHowto>
- <http://www.opinsys.fi/en/user-management-with-sssd-on-shared-laptops>

Chapter 2. Integration of Linux/Unix systems into a UCS domain


These are general instructions for the integration of Unix/Linux-based non-UCS systems - referred to in the following simply as Unix systems - in the trust context of the UCS domain.

The integration of Ubuntu clients is documented with example step-by-step instructions in Chapter 1.

The integration of Mac OS X clients is documented with example step-by-step instructions in the UCS manual. Mac OS systems use a deviating domain integration based on Samba 4.

Not all integration steps need to be performed. In this way, for example, a Unix system can merely be integrated in the IP management and access the NTP server without integrating the system in the UCS user management (e.g., if it is a database server on which no user login is performed anyway).


2.1. Managing the systems in the Univention Management Console

Feedback 

A **Computer: Linux** object can be created in the UMC computer management. This allows the integration of the Unix system in the DNS/DHCP and network administration of the Univention Management Console

If the Nagios support is enabled under [Options], remote Nagios checks can also be applied against the system.


2.2. Configuration of the name resolution

Feedback 

The Unix system should use a name server from the UCS domain: All UCS domain controllers (i.e., master domain controller, backup domain controller and slave domain controller) operate a DNS server. One or more of these UCS system should be entered in the `/etc/resolv.conf`, e.g.:

```
domain example.com
nameserver 10.200.3.108
nameserver 10.200.3.99
```

2.3. Configuration of the time server


Feedback 

All UCS domain controllers (i.e., master domain controller, backup domain controller and slave domain controller) operate a NTP server.

The configuration differs depending on the NTP software used, but is set under `/etc/ntp.conf` on most Linux systems, e.g.:

```
server master.example.com
server backup.example.com
```

2.4. Access to user and group information of the UCS domain

Feedback 

The *Name Service Switch* (NSS) is an interface for configuring the data sources for users, groups and computers. NSS is present on all Linux versions and most Unix systems.

If the Unix system used provides support for an NSS module for LDAP access - as is the case in most Linux distributions - user and group information can be read out of the UCS LDAP directory.

The configuration files of the NSS LDAP module differ depending on the Linux/Unix version.

As a general rule, the following settings must be set there:


- The DN of the LDAP base of the UCS domain (saved in the Univention Configuration Registry variable `ldap/base` on UCS servers) needs to be configured on the system.
- The LDAP server, ports and authentication credentials to be used. The fully qualified domain names of one or more UCS domain controllers should be entered here. In the default setting, UCS LDAP servers only allow authenticated LDAP access.
- In the standard setting, only TLS-secured access is possible on UCS-LDAP servers. The accessing Unix system must therefore use the root certificate of the UCS-CA. The certificate can be found on the master domain controller in the file `/etc/univention/ssl/udsCA/CACert.pem` and can be copied into any directory, e.g., `/etc/ucs-ssl/`. The UCS root certificate must then be configured in the LDAP configuration files. If the Unix system uses OpenLDAP as the LDAP implementation, it is usually the file `/etc/openldap/ldap.conf` or `/etc/ldap/ldap.conf`. The line for OpenLDAP is as follows:

```
TLS_CACERT /etc/ucs-ssl/CACert.pem
```

If the NSS LDAP service has been set up correctly, the following two commands should output all users and groups:

```
getent passwd
getent group
```

2.5. Integrating into Kerberos

Feedback 

UCS employs the Kerberos implementation Heimdal. For this reason, Heimdal should also be used to access the Kerberos realm on the Unix system. Only the Heimdal client libraries need to be installed on the Unix system.

Kerberos requires correct time synchronisation, see Section 2.2.

The configuration is performed in the `/etc/krb5.conf` file on most systems. Here is an example configuration:

- `KERBEROSREALM` must be replaced by the name of the UCS Kerberos realm (saved in the Univention Configuration Registry variable `kerberos/realm`).
- `MASTERIP` must be replaced by the IP address of the master domain controller.
- `MASTERFQDN` must be replaced by the fully qualified domain name of the master domain controller.

```
[libdefaults]
    default_realm = KERBEROSREALM
    default_tkt_enctypes = arcfour-hmac-md5 des-cbc-md5 des3-hmac-sha1 \
        des-cbc-crc des-cbc-md4 des3-cbc-sha1 aes128-cts-hmac-sha1-96 \
        aes256-cts-hmac-sha1-96
    permitted_enctypes = des3-hmac-sha1 des-cbc-crc des-cbc-md4 \
        des-cbc-md5 des3-cbc-sha1 arcfour-hmac-md5 \
        aes128-cts-hmac-sha1-96 aes256-cts-hmac-sha1-96
    allow_weak_crypto=true
    kdc_timesync = 1
```

Accessing a UCS print server

```
ccache_type = 4
forwardable = true
proxiabile = true
kdc_timesync = 1


[realms]
KERBEROSREALM = {
    kdc = MASTERIP MASTERFQDN
    admin_server = MASTERIP MASTERFQDN
    kpasswd_server = MASTERIP MASTERFQDN
}
```

The Heimdal PAM module then needs to be installed. In general, the installation of the module should adapt the PAM configuration automatically.

Then Kerberos authentication during login should work via PAM and password changes should be possible via kpasswd.

To allow SSH logins via Kerberos, the options *GSSAPIAuthentication* and *GSSAPIKeyExchange* should be set to *yes* in the configuration file of the SSH daemon (typically `/etc/ssh/sshd_config`).

2.6. Accessing a UCS print server

Feedback 

UCS uses the *Common Unix Printing System* (CUPS) to implement print services. The Unix system can use the UCS print servers by installing the CUPS client programs. In addition the CUPS server needs to be configured for the clients, typically in the configuration file `/etc/cups/client.conf`, e.g.:

```
ServerName printserver.example.com
```